

GrdFindInfo Struct Reference

Description of fields that can be use in the search dongle.

```
#include <grdMobileSDK.h>
```

Public Attributes

- uint32_t **publicCode**
Public code (zero means finding all dongles)
- uint32_t **dongleId**
Dongle ID (unique)
- uint32_t **model**
Dongle model/models (combination of GrdFMM_xxx flags)
- uint16_t **feature**
Dongle feature flags (combination of GrdDT_xxx flags)
- uint16_t **serialNumber**
Serial number.
- uint16_t **mask**
Bit mask.
- uint8_t **programNumber**
Program number.
- uint8_t **programVersion**
Program version.

Detailed Description

Description of fields that can be use in the search dongle.

The documentation for this struct was generated from the following file:

- **grdMobileSDK.h**